

Keysight Technologies

CX3300 Current Waveform Analyzer

Quick Operation Guide

How to overlay multiple acquisitions

1. ON : Display > Persistence > Infinity
 - 1-1. Click the “Display” icon on the Tool Palette.
 - 1-2. Select “Persistence” on the Display tool palette.
 - 1-3. Drag and drop the “Infinity” icon on the Display tool palette onto the area of interest on the waveform.



Next page

2. OFF : Display > Persistence > Normal
 - 2-1. Click the “Display” icon on the Tool Palette.
 - 2-2. Select “Persistence” on the Display tool palette.
 - 2-3. Drag and drop the “Normal” icon on the Display tool palette onto the area of interest on the waveform.

